



“Installation of TeraData 13.0”

This document briefs you the step by step approach to download, Install, Configuring Teradata 13.0. Join our professional training program to learn from the experts

History:

Version	Description Change	Author	Publish Date
0.1	Initial Draft	Lokesh kumar	6 th Jun 2011
0.1	1 st Review	Amit Sharma	7 th Jun 2011
01.	2 nd Review	Manohar Krishna	7 th Jun 2011

Amit Sharma

<http://bispobiee.blogspot.com/>
essbasexpects.wordpress.com
learnodi.wordpress.com
learnoraclebi.wordpress.com
learnplanning.wordpress.com
learnsqlquery.wordpress.com
learncognosreports.wordpress.com
learnsoa.wordpress.com
odinetwork.blogspot.com
bispteradata.wordpress.com

Table of Contents

1). Prerequisites.....	3
2). Downloaded setup files	4
3). Extract the Teradata setup files and run the software.....	5
4). Install all components one by one	7
5). Post install	11
6). Verifying software installation.....	11

1). Prerequisites

Operating System Support

Microsoft Windows XP with SP3

Microsoft Windows Server 2003 with SP2

Microsoft Windows Vista

Microsoft Windows Server 2008

Microsoft Windows 7

Other software required

MS Dotnet Framework 2.0 or later

Hardware Specification

Disk Space: 2.5GB to 12GB

Memory: 1GB


2). Downloaded setup files

Click on Download link and save in your computer

<http://www.teradata.com/express-download.aspx?dlid=2>

Other FAQ about Teradata software installation please follow link


<http://www.teradata.com/express/faq13/>



3). Extract the Teradata setup files and run the software


3.1). Put the setup into a folder and extract it.

3.2) Click on setup and run. Wait for next window.



4). Software screen

4.1) After run the setup you will find screen. Click on "Next- Main Menu".




5). Enter into Menu

Click “Installs Teradata 13.0 and Tools”. From Main Menu.



6). It checks automatically for your prerequisites,

This installation is done on below platform. If any warning note is given in this step than please check your system configuration. Otherwise click on next.\





7). Install all components one by one

****Note:** Do not restart computer every time. After complete installation of all components only once you should restart computer.


7.1) First of all Install Teardata BYNET Driver.

Click on (A) Teardata BYNET Driver → (B) waiting for installation→(C) Click on No button.



7.2) Install Teradata Database

Teradata Database → Next button → select database size (according to your use) → select destination folder (where you want to store database) → Finish



Teradata Database 13.00.00.12 only for non production purpose.

Teradata express tool, MS c++ compiler and jre (only for java External stored procedures) is needed for install



Compiler and jre available in additional software.

In next screen you will be get warning message about copyright law click on next.

Choose memory space according to your use. Only for practice we can take 512MB .




Select destination folder where you will store your Teradata database. Default drive will be c:\ drive. You can change your position.



7.3) Install Teradata Express Tools


Teradata Express tools → Typical and Next button → select all and next → Finish





Here you will find two choices
Typical- here we choose typical option than next.
Custom



Select all functionality of software and go to next click.



Installation process



7.4.) Teradata tools and utilities

Also install Teradata Tools and utilities.

7.5.) TeraData Ware House Miner



There is no need to install TD WareHouse Miner

7.6.) Additional Softwares

It is not mandatory to install Additional Softwares.

8).Finish Installation

Click on the highlighted button and wait for restart the computer



Click on yes and ok

9). Post install

After restart your computer you will find the new icons on your desktop.

1. Teradata Parallel Transporter Wizard 13.0
2. Teradata Service Control



10). Verifying software installation

There are two ways to start

A.) Click on Teradata service Control icon present on desktop. Click on start teradata button present on window. Arrow is showing where to click and second red box showing current status of service control.



After start window will show you current running status. For stop click on same place "stop teradata".



B.) Go to start→ All programs→Teradata DataBase Express 13.0→ Teradata service control→ click and wait for window

